

КАК – Windows Mobile 6.1 tips

КАК – исправить SMS в Windows Mobile 6.1	1
КАК – Переместить My Documents на карту памяти	1
КАК – Смена директории для хранения рингтонов	1
КАК – Перенос кеша эксплорера.....	2

КАК – исправить SMS в Windows Mobile 6.1

Чтобы переключить SMS из режима conversation (разговор) в нормальный вид используется ключ реестра

```
[HKEY_CURRENT_USER\Software\Microsoft\Inbox\Settings\OEM]  
"SMSInboxThreadingDisabled"=dword:00000001
```

КАК – Переместить My Documents на карту памяти

Activesync File Synchronization to SD or CF Card

After some testing on my part, I am able to use file synchronization in activesync to sync files to my SD or CF card instead of going to the My Documents folder in the internal memory. Since I use file synchronization for certain apps (such as eWallet) I can now save space in RAM and sync the files to the SD or CF cards on my 2215. The trick is a simple registry tweak and then a soft reset. You will need a registry editor to do this. I also recommend doing a backup of your PPC first and also backing up the PPC My Documents folder on your desktop so that you won't lose any files if you make a mistake. This is how I did it:

1. Done my backups.
2. Turned off File Synchronization in Activesync on my desktop.
3. Create a Folder on your SD or CF card for your sync'ed files (My Documents for example). Remember the folder name as you will need it later.
4. Copy the files from the PPC My Documents folder on your desktop to the newly created folder on your SD or CF card. You could either use a card reader/writer or activesync to do this.
5. Open the registry editor. Goto \HKLM\Software\Microsoft\Windows CE Services. There are two keys to edit; the FileSyncPath and the NoSubFolderIn keys. These keys contain the path of where your files are sync'ed to. The FileSyncPath key should be modified to point to your newly created folder on your SD or CF card. In my case I modified it to \SD Card\My Documents. Modify the NoSubFolderIn to \SD Card\My Documents\ (in my case). Save and exit the registry app.
6. Soft Reset your PPC.
7. Turn File Synchronization back on and cradle your PPC. The files should now sync to your SD or CF card.

Once you have sync'ed a couple of times and you are comfortable, you can delete the files in \My Documents. Be careful and not delete any notes that you have in the folder that has been created with the Notes app. Also you might find file synchronization to be a little slower due to the fact that you are now writing to the SD or CF card instead of the internal RAM.

КАК – Смена директории для хранения рингтонов

Путь: HKCU\ControlPanel\SoundCategories\Ring\
Ищем Directory

Пишем, например, следующее: \Storage Card\. Папка по умолчанию - \Windows\Rings или \Windows\. Чтобы вернуть папку по умолчанию, надо ввести: \Windows\Rings\.

Работает только если указать \Storage Card\ а вот путь \Storage Card\Rings\ уже не хочет. 😞

По любому звонки удалось туда перенести и то хорошо. 😊

КАК – Изменение пути хранения электронной почты и вложений в Pocket Outlook

Для Windows Mobile 6:

Путь: HKLM\System\Inbox\Settings\
Ищем PropertyPath

Путь: HKCU\Software\Microsoft\MAPI\
Ищем AttachPath

Можно указать такой путь: \Storage Card\Mail\Attachments.

Ищем AttachPath

Можно указать такой путь: \Storage Card\Mail\Attachments.

В обоих случаях, чтобы вернуть установки по умолчанию, удалите созданные параметры.

Как раз таки в пути HKLM\System\Inbox\Settings\ нашел только AttachPath и там перебил путь на нужный. Второго PropertyPath вообще ни где не нашел. Соответственно хотелось бы полностью перенести почту на флешку.

КАК – Перенос кеша эксплорера.

Есть например такой способ:

Изменяем местонахождение папки Temporary Internet Files

Путь: HKCU\Software\Microsoft\Windows\CurrentVersion\Explorer\Shell Folders\
Ищем Cache

Ищем Cache

Можно указать такой путь: \Storage Card\cacheie. Путь по умолчанию:

\Windows\Profiles\guest\Temporary Internet Files.

Выставил пусть на карту памяти в папку Temp. Походу тоже не работает. Во всяком случае файлов кеша что-то вообще там не видно при работе.