

Access your Synology NAS over the Internet and share files

https://www.synology.com/en-us/knowledgebase/DSM/help/DSM/Tutorial/cloud_set_up_quickconnect




Overview


With QuickConnect, you can easily connect to your Synology NAS over the Internet without the hassle of setting up port forwarding rules or other complicated network settings. QuickConnect allows you to connect via a simple customizable address like **Quickconnect.to/example**.

1. Set up QuickConnect


1. Go to **Control Panel > QuickConnect**.
2. Check the **Enable QuickConnect** box.




3. If you do not have a Synology Account, click **Log in to or register a Synology Account**. Enter the required information and click **OK**. If you already have a Synology Account, enter your account information.




4. Create your own QuickConnect ID in the **QuickConnect ID** field. Then click **Apply**.




5. Your QuickConnect link information will appear. Use these links to access your Synology NAS. In this example, the address for DSM is **http://Quickconnect.to/YourID**.



6. If you do not see the QuickConnect DSM link, click **Advanced** and make sure DSM is enabled.




7. You can now use the QuickConnect DSM link to access your Synology NAS!




2. Share files on your NAS using QuickConnect

With QuickConnect enabled, you can easily share files stored on your Synology NAS to anyone without worrying about port forwarding.

1. First enable HTTPS connection to safely share your files. Go to **Control Panel > Network**.
2. Check the **Enable HTTPS connection** box and click **Apply**.




3. Then enable file sharing for QuickConnect. Go to **Control Panel > QuickConnect**.
4. Click on **Advanced** and make sure the box of **File Sharing** is checked.



Note:

When configuring advanced QuickConnect settings, we recommend that you log in to DSM using the local IP address or domain name of your Synology NAS.

5. You are ready to start sharing files using QuickConnect. Open **File Station** and right-click the file or folder that you want to share. Then click **Share file links** from the context menu.



6. A file sharing link is generated. Simply share this link with family and friends to download the shared folder/file.

Share File Links

Validity period

Get QR Code

Create shared link(s) to allow people without DSM user credentials to download the shared file(s).

File path:

/test/Test.txt

For file sharing, copy the links below or send them via **the Default Email** or **Mail**. 

Sharing link:

<http://gofile.me/6oFlF/ewIajBAe>